Section 1

Step 1: Log in to Azure Preview Portal (<u>https://portal.azure.com</u>)

Step 2: Click "New"



Step 3: Select "MarketPlace"



Step 4: Search for FortiGate

+ https://portal.azure.com	m/# の マ 🔒 🕈 📑 Everything - Micros	oft Azure ×					☆ 🕸
Microsoft Azure 🗸 🕨	New > Marketplace > Everything	م	Û	I - E	?	Martin Twombly DEFAULT DIRECTORY (AZURE	
≡	* _ 🗆 ×	Eventhing					
+ New	e	Everything					
📦 Resource groups		▼ Filter					
🕒 Recent							
All resources		/ loragate					
🔕 Web Apps	2	NAME				∧ PU	BLISHER
SQL databases	e	FortiGate NGFW	Single VN			Fo	rtinet
Virtual machines (classic)							

Step 5: Click Create



Step 6: Fill in Basics

Basics			×
* FortiGate VM Name ⊕			_
FortiGate		~	
* FortiGate Administrative User	name 🖲		
fortiadmin		~	
* FortiGate Password 🛛			
•••••		 ✓ 	
* c c i			
Confirm password			1
*******		~	
* Subscription			-
Fortinet Engineering		/	
* Resource group			-
fortinetrg	>	< 🗸	
Select existing			_
* Location		>	

Step 7: Configure Network and Storage Settings

1	Basics 🗸	* Virtual network (new) FortigateProtectedVNet	* Outside Subnet name PublicFacingSubnet ✓
2	 Network and Storage Settings > Configure the network and sto 	Subnets Configure subnets Virtual machine size	* Outside Subnet address prefix 10.2.0.0/24 ✓
3	FortiGate IP Address Assignme > Configure the Public IP and th	1x Standard A3 * Storage Account Configure required settings	* Inside Subnet name FortigateProtectedSubnet ✓ * Inside Subnet address prefix
4	Summary >		10.2.1.0/24

Virtual Network: Here, you can either create a new Virtual Network or select an existing one. If you select an existing virtual network, it will need to have at least two subnets in order for the FortiGate to route between them. In a typical deployment, the "outside" subnet just connects the FortiGate outside interface to the Azure Public Load Balancer. Thus, it does not need to be very large.

Machine Size: The prices listed for machine sizes are for the instance usage only. The FortiGate license must be purchased through a Fortinet partner. The machine size is limited to those options which support multiple NICs. As MS adds more interfaces to smaller instance types, we will enable them. If more than two NICs are required, you will need to deploy a custom template at this point. Please contact the Azure team (azuretech@fortinet.com) for assistance.

Storage Account: You can create a new storage account or select an existing one. All resources should be in the same location (in this example: East US).

Step 8: Configure IP Settings



Public IP Address: Typically, this will be associated with a load balancer and will be used to access your FortiGate from the internet (as well as resources behind it). If you are using an ExpressRoute or Azure VPN to access your virtual network, you may prefer to select "none"

Public IP Address Type: A 'Static' public IP address will be reserved across reboots and shut down states. A 'Dynamic' address will be reassigned.

Outside and Inside Addresses: These fields are prepopulated with the first useable address in the subnet (Azure uses the first three addresses in each subnet). However, if deploying to an existing subnet, this address may be in use already. You must verify that the IP addresses are available and in the correct subnet as this level of verification is not yet available within the Marketplace deployment logic.

Step 9: View Summary

Step 10: Click "Create"

Step 11: Wait



This typically takes around 10 minutes, but may vary depending on location and number of resources requested.

Step 12: Once Deployed, you should be redirected to a screen which shows all the resources instantiated by the template.

+ https://portal.azure.com/	/# 🔎 👻 📑 Settings - Microsoft Azure	×	a faat Barran	6 ☆ 53
Microsoft Azure 🗸 De	emoRG > Settings	🖉 😲 🤇	⁹ 🔅 ⑦ _{DEFAULT}	Martin Twombly
≡			* _ 🗆 ×	
+ New	DemoRG Resource group			Settings DemoRG
📦 Resource groups				
🕒 Recent	Essentials ^		CL 88 🖉	Search settings
All resources	Subscription name Fortinet Engineering	Subscription ID 2f96c44c-cfb2-4621-bd3	36-65ba45185e0c	Properties
🔇 Web Apps	Last deployment 11/5/2015 (Succeeded)	Location West US		🗳 Users
👼 SQL databases			All settings \rightarrow	Tags
👰 Virtual machines (classic)	Summary			
Virtual machines	Resources			
Cloud services (classic)	FortiGate			
Subscriptions	💠 publicLB			
🚸 Load balancers	Nico			
Storage accounts	DefaultNSG			
Virtual networks	LBPublicIP			
V VII (uar networks	ProtectedSubnetRoutes			
Browse 📏	PublicFacingSubnetRoutes			
	FortiGateVNET			
	Monitoring			
	Events	Alert	rules	

+ https://portal.azure.c	om/# ♀ ♣ ♂ 📕 Set	tings - Microsoft Azure 🛛 🗙			
Microsoft Azure 🗸	DemoRG > LBPublicI	P > Settings	ᡗ م	1 🛱 🔿	Martin Twombly DEFAULT DIRECTORY (AZURE
≡ + New	* _ ×	LBPublicIP Public IP address			* _ 🗆 ×
📦 Resource groups		Settings Dissociate	Delete		
🕒 Recent	12 4R 🗸	Essentials ^			CA 19. 🖉
All resources	ba45185e0c	Resource group DemoRG Location		DNS name twomblyfgatede IP address	oloy.westus.cloudapp.azur
🔕 Web Apps		West US		104.42.237.34	
sQL databases	All settings →	Fortinet Engineering		publicLB	
Virtual machines (classic)		2f96c44c-cfb2-4621-bo	d36-65ba45185e0c		
Virtual machines					All settings 🔿
Cloud services (classic)		Operations			
Subscriptions		Events LBPUBLICIP			
💠 Load balancers		4			
Storage accounts		2			
Virtual networks		1			
Browse >		0			

Step 13: Select the public IP resource to get your DNS name or public IP address

Step 14: Connect to your Azure FortiGate virtual appliance via HTTPS or SSH

Note: The template also redirects ports 500, 4500, and 1701 to the FortiGate in order to support VPN connections. Additional ports can be added in the load balancer NAT rules post deployment.

Step 15: License your Azure FortiGate virtual appliance

Currently our Azure Marketplace deployment only supports BYOL licenses. This means, you will need to purchase Azure specific licenses for the virtual appliance. The licenses are FG-VM02-AZ, FG-VM04-AZ and FG-VM08-AZ.

Note: If you have a mismatch between the VM size and the license (ie. more CPUs assigned to the VM than are licensed), you will receive an error message, and the FortiGate configuration will not be accessible.